

Directory Synchronization Maintenance

In order to download addresses from the central directory, you must create a profile for each node in your network from which you want to obtain information. By creating a profile, you can delimit the addressee types you wish to download, how the addresses are downloaded, the security levels which will apply for the addresses and where the addresses will be stored when they are imported to your Con-nect node.

This chapter covers the following topics:

- Directory Synchronization Maintenance Menu
 - Directory Synchronization Maintenance
 - De-Install Directory Synchronization
 - Add Profiles
 - Maintain Profiles
 - Maintain Log Records
-

Directory Synchronization Maintenance Menu

When you select the Directory Synchronization Maintenance function, the screen below is displayed.

```

5:40 PM          * * * C O N - N E C T 3 * * *          14.Feb.94
Cabinet LS      Directory Synchronization Maintenance      OLAP

Select a Function:  _ Directory Synchronization Maintenance
                   _ De-Install Directory Synchronization
                   _ Add Profiles
                   _ Maintain Profiles
                   _ Maintain Log Information

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Menu  Quit  DMain DeIns AProf MProf MLog
Mark item(s) from the list above or press a PF-key

```

You select the function you want with any character and press ENTER to access that function.

Directory Synchronization Maintenance

This section covers the following topics:

- Directory Synchronization Maintenance Screen
- Erase Directory Synchronization Maintenance Data
- Reset Upload Transaction Counter
- Reset Download Transaction Counter

Directory Synchronization Maintenance Screen

Information which is required to maintain your directory synchronization is partially provided automatically and partially provided by you. It is very important that you ensure that the information pertaining to the central directory is correct. If not, any attempt to upload and/or download will result in an error message.

```

5:41 PM                      * * *   C O N - N E C T   3   * * *                      14.Feb.94
Cabinet LS                    Directory Synchronization Maintenance                      OLAP07

Central Directory Name:      DAEFCOC_
Central Directory DBID:      180                      Central Directory FNR: 12_

Transport Service Node Name: CEDARRP                      Mod. TS Node Name:
CON-NECT DBID:              180                      CON-NECT FNR:          30

Synchronization Abilities:  B up/download                      Version:      1.1
Log Level:                  3                      Transaction Limit: 50__
Set Addresses for Upload:   AUTO      Addr. _ Bull. _ Cab. _ Ext. _ Name _

MRU Transaction Counter:    0000000000000000000000056591
MRD Transaction Counter:    0000000000000000000000056600

Date Last Uploaded:        19940209                      Date Last Downloaded: 19940209
Time:                      15:51:24.5                      Time:          16:14:48.7

Date Modified: 19940209   Time Modified: 16:14                      Author ID:   LS

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Menu  Quit  Erase  Save  RsMRU  RsMRD                      Cancel
Make the required changes and press a PF-key

```

Central Directory Name

Name of the central directory.

Do not modify this field unless your central directory administrator has informed you that the name has been changed. Additionally, this field is not used to switch to another central directory.

If you modify the central directory name on this screen, a confirmation window is displayed and you are informed that the uploaded and imported addresses stored in cabinet SYSCNT will be modified. Enter *Y* and press ENTER to confirm, or press ENTER to cancel the modification.

Central Directory DBID

Database ID of central directory. This field along with the Central Directory FNR field defines the LFILE parameter used by the central directory. The LFILE parameter is assigned when you press PF3 or PF5 and when the upload and download functions are started with the administration programs.

Do not modify this field unless your central directory administrator informs you that it has been modified.

The value you specify here is not verified until you perform an upload or download. If the DBID is not correct, a Con-nect error message is displayed. Therefore, it is important to ensure that you specify the correct DBID.

Central Directory FNR

File number of central directory. This field along with the Central Directory DBID field defines the LFILE parameter used by the central directory. The LFILE parameter is assigned when you press PF3 or PF5 and when the upload and download functions are started with the administration programs.

Do not modify this field unless your central directory administrator informs you that it has been modified.

The value you specify here is not verified until you perform an upload or download. If the FNR is not correct, Con-nect error message is displayed. Therefore, it is important to ensure that you specify the correct FNR.

Transport Service Node Name

Automatically provided. Name of your local transport service node.

Mod. TS Node Name

Automatically provided when you rename your transport service node with the Define Local Node function. See *Transport Service Node ID*.

Previous transport service node name, which is displayed until all addresses defined to the transport service are modified on the central directory. The modification process can take some time. If, however, the previous node name remains for more than a couple of hours, see *Define Local Node Function - Rename Transport Service Node Name*.

Con-nect DBID

Automatically provided. Database ID of your local Con-nect node.

Con-nect FNR

Automatically provided. File number of your local Con-nect node.

Note:

The values in fields Con-nect DBID and Con-nect FNR are verified with the information stored in the central directory each time you perform an upload or download.

Synchronization Abilities

Automatically provided via the Central Directory Maintenance function (maintained by your central directory administrator). Indicates how your Con-nect node interacts with the central directory. See *Central Directory*.

- U Permitted to upload local addresses to central directory.
- D Permitted to download addresses from the central directory.
- B Permitted to upload and download addresses to/from the central directory.

Version

Automatically provided. Version of the directory synchronization programs used on your Con-nect node to upload and/or download addresses.

Log Level

Designates the type of event that will cause a record to be written to the log file. The values used are:

- 0 Default. Log significant events (e.g. uploads, downloads) which occur.
- 1 Log events that are traced by the system. It is recommended that log level one should only be used when additional information is required.
- 2 Log all programs that are traced. It is recommended that log level two should only be used when additional information is required.
- 3 Log all events that occur. It is recommended that log level three should only be used when additional information is required.

Transaction Limit

The value is used by the upload and download processes to determine the number of addresses which are read before an end of transaction is performed.

Set Addresses for Upload

Determines whether new addresses in your SYSCNT cabinet will be automatically (Auto) or manually (Manl) set for upload to the central directory. Default - Auto. You mark the addressee type(s) you want to adhere to this rule.

Standalone cabinets must always be uploaded manually.

For example, if you have specified automatic upload for addressee type Cabinet and you add a shared cabinet, the next time you perform the Upload Addresses function, this cabinet will be automatically uploaded to the central directory. You need not manually set it for upload.

If you display the shared cabinet with the Upload Address Maintenance function before performing an upload, the status of the cabinet will be blank, even though it has been automatically set for the next upload.

MRU Transaction Counter

Automatically incremented with each upload. Last transaction number assigned to local address during upload procedure to the central directory. The number displayed here is also recorded in the central directory. It is also used to verify that the central directory and your local node are synchronized.

You can reset this field to 0 with PF6. See *Reset Upload Transaction Counter*.

MRD Transaction Counter

Automatically incremented. Transaction number assigned to last address downloaded from the central directory. The number displayed here is also recorded in the central directory. It is also used to verify that the central directory and your local node are synchronized.

You can reset this field to 0 with PF7. See *Reset Download Transaction Counter*.

Date Last Uploaded

Date last upload occurred.

Time Last Uploaded

Time last upload occurred.

Date Last Downloaded

Date last download occurred.

Time Last Downloaded

Time last download occurred.

Date Modified

Date of last modification.

Time Modified

Time of last modification.

Author ID

Identifies user who made last modifications.

To save your modifications, press PF5. If you have modified the central directory name on your Con-nect node, a confirmation window is displayed. It shows the number of addresses in your SYSCNT cabinet that will be modified if you confirm the modification. To confirm the modification, enter *Y*, or press ENTER to cancel the modification.

Erase Directory Synchronization Maintenance Data

You can press PF4 to de-install the directory synchronization. As a result, a confirmation window is displayed. Enter *Y* and press ENTER to de-install, or press ENTER to cancel. In contrast to the De-Install Directory Synchronization function, only the maintenance data displayed on this screen is deleted. The synchronization profiles, downloaded records and cabinets uploaded to the central directory are not deleted. See *De-Install Directory Synchronization*.

Reset Upload Transaction Counter

You can reset the upload transaction counter to zero to force a total upload to the central directory. To reset the transaction counter, press PF6 and with the next upload, the system will perform a total upload.

Reset Download Transaction Counter

You can reset the download transaction counter to zero to force a total download from the central directory. To reset the transaction counter, press PF7 and with the next download, the system will perform a total download.

De-Install Directory Synchronization

When you select the De-Install Directory Synchronization function, the resulting window displays the total number of synchronization profiles, downloaded addresses and maintenance data (defined with the Directory Synchronization Maintenance function) stored on your Con-nect node that will be deleted when the directory synchronization is de-installed. It also displays the total number of addresses you have imported to your Con-nect node. The imported addresses will not be deleted from your node, however, they will be unlinked from the central directory. This means that any modifications made to the addresses on the central directory will not be updated on your Con-nect node.

If you want to delete only the maintenance data, see *Directory Synchronization Maintenance*.

```

5:44 PM          * * * C O N - N E C T 3 * * *          14.Feb.94
Cabinet LS      Directory Synchronization Maintenance      OLAP70

Select a Function:      _ Directory Synchronization Maintenance

+-----+
!   The Directory Synchronization will   ! ion
!   be de-installed!                     !
!                                         !
!   80          Synchronization Objects   !
!               will be deleted.          !
!   97          Synchronization Addresses !
!               will be unlinked.         !
!   Imported Addresses are not deleted.   !
!                                         !
!   Enter Y to confirm: N                 !
!                                         !
!   Press ENTER to continue               !
+-----+

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Menu  Quit  DMain DeIns AProf MProf MLog
Make the required changes and press a PF-key

```

To de-install, enter *Y* and press ENTER.

To cancel the de-install, press ENTER.

Add Profiles

This section covers the following topics:

- Add Profiles Screen
- Download
- Import

Add Profiles Screen

When the download function is performed, only the addresses which correspond with the delimiting factors (node and addressee type) of a profile you have defined will be downloaded from the central directory.

The Add Profiles function is used to create the profiles. When you select this function, all nodes which interact with the central directory and the possible addressee types are displayed.

```

5:17 PM          * * * C O N - N E C T 3 * * *          14.Feb.94
Cabinet LS      Directory Synchronization - Add Profiles      OLIP90

Node Name Address Cabinet Ext.Address Bulletin Board Last Name
-----
ATLANTA
BOSTON          -
CEDARRPS
DENVER          -
SEATTLE         -

Position to Node Name _____

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Menu  Quit          -      +      --      ++
Select by marking with any character

```

If you have previously created a profile for an addressee type on a particular node, the column for that addressee type is empty and you are unable to select the addressee type. You can use the Maintain Profiles function to display, modify or delete a previously created profile. See *Maintain Profiles*.

Mark the addressee types you want for each node and press ENTER. The resulting screen, as shown below, is displayed for each addressee type and node you selected.

| | | | |
|---|--|--------------------|-----------|
| 5:32 PM | * * * C O N - N E C T 3 * * * | | 14.Feb.94 |
| Cabinet LS | Directory Synchronization - Add Profile | | OLIP90 |
| Download | | Import Rule Syntax | |
| CD Name: | DAEFCOC_ | | |
| Node Name: | DENVER__ | #1 #2 ... | |
| Addressee Type: | Cabinet_____ | #1 Mail ID | |
| Date Last Downloaded: | 0000-00-00 00:00:00.0 | #2 Node Name | |
| Highest Transaction ID: | 0 | #3 Last Name | |
| | (Set to zero with RESET PF-key) | #4 First Name | |
| Import | | #5 CD Name | |
| Include First/Last Name: | X (Mark to include) | #6 Alias | |
| Separator: | . | #7 Addressee | |
| Import Rule: | #1 #2_____ | | |
| Exception Import Rule: | #6_____ | | |
| Batch Import Mode: | X Automatic _ Controlled | | |
| Target Cabinet: | SYSCNT__ | | |
| Folder: | Work_____ | | |
| File: | _____ | | |
| Security Levels: | 7 Read 7 Modify 7 Copy 7 Print | | |
| | (Original security levels used when blank) | | |
| Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--- | | | |
| Menu Quit | | Cancel | |
| Make the required changes and press a PF-key | | | |

Download

The values displayed here are automatically provided:

CD Name

Name of the central directory.

Node Name

Name of node to which this profile applies.

Addressee Type

Type of addressees which are to be downloaded.

Date Last Downloaded

Date and time of last download.

Highest Transaction ID

Each time an address is uploaded to the central directory, whether for the first time or when modified, a transaction ID is assigned to the address.

The number displayed here is the highest transaction ID which has been downloaded to your local Con-nect node. The next time you perform a download, the system will use this number as an indicator to begin downloading the address with the next highest transaction ID.

Import

The values you specify here determine, for example, how each downloaded addressee is imported to your SYSCNT cabinet and how the imported addressee is uniquely identified on your Con-nect node.

Note:

Import rules and exception import rules can also be defined with user exit USR0060C. Once you execute USR0060C, the fields Include First/Last Name, Separator, Import Rule and Exception Import Rule are not displayed in the "Directory Synchronization - Add Profile" screen. USR0060C can be either performed online or in batch mode. For further information, see *User Exit USR0060C*.

Include First/Last Name

Pertains only to addressee type Cabinet. Designates whether the first and last name of a private cabinet will be additionally used to create the address' nickname. If this field is blank, the first and last name will not be used.

Separator

Separator character. A unique nickname is created for each imported address. The values which are used to create this nickname are determined in the "Import Rule" field below. The separator character that you specify here is inserted between the different values. A separator character can be, for example, the dollar sign (\$), or comma (.).

You cannot use the asterisk (*) as a separator and, depending upon your environment, there may be other characters which cannot be used.

Default is: " " (blank).

Import Rule

Defines which address information is used to create the address' nickname on your local node. If you specify more than one value here they must be separated by a blank. For example #2 #3.

If you have specified a separator character in the field above, this character will be used to separate the values when the mail ID is created; it is not entered here.

Note:

When adding a profile for addressee type bulletin board, it is recommended that you use the defaults for this field.

The following values can be specified:

- #1 Addressee's user ID.
- #2 Node name from which address originates.
- #3 Addressee's last name.
- #4 Addressee's first name.
- #5 Name of central directory from which address was downloaded.
- #6 A unique ID which is assigned by the system to each addressee uploaded to the central directory.
- #7 The addressee's name, which can be one of the following: the description or name of a cabinet, user's full name, nickname, bulletin board or external address.

Exception Import Rule

Used to override the import rule, if in this case the import rule would create a duplicate nickname.

Batch Import Mode

Determines whether or not the addresses are imported in batch mode. You can select one of the following options:

- Automatic Address data is automatically imported to your Con-nect node when you run utility B20002 "Directory Synchronization - Download".
- Controlled All addresses which correspond to this profile are not imported during the execution of utility B20002 "Directory Synchronization - Download". You must download the addressees online (using the directory synchronization administration Download Addresses function).

Target Cabinet

Cabinet to which addresses are imported - this is always cabinet SYSCNT.

Folder

Folder in target cabinet to which addresses are imported.

File

File in target cabinet to which addresses are imported.

Default Security Level

Security levels (read, modify, copy, print) assigned to each address when they are imported to your local node. If, in the case of addresses of type address and external, the security levels are left blank, the security levels assigned to the addresses on the originating node are used. See *Cabinet Profile*.

When you have completed your specifications, press PF3 to save the profile.

To define the next addressee type, press PF4.

Maintain Profiles

This section covers the following topics:

- Maintain Profiles Screen
- Display Profile
- Erase Profile
- Modify Profile

Maintain Profiles Screen

The Maintain Profiles function is used to maintain the profiles you created with the Add Initial Profile function.

```

5:50 PM                * * *   C O N - N E C T   3   * * *                23.Feb.95
Cabinet LS              Directory Synchronization - Maintain Profiles          OLIP92

Cmd Node Name  Addressee Type      Date Last Downloaded  Mode      CD Name
---  -
__ BOSTON      Address              1994-02-09 16:37:50.1  AUTO      DAEFCOC
__ DENVER      Address              1994-02-09 16:37:50.3  CNTL      DAEFCOC
__ DENVER      Bulletin             1994-02-09 16:37:50.4  CNTL      DAEFCOC
__ DENVER      Cabinet              1994-02-09 16:37:50.5  CNTL      DAEFCOC
__ SEATTLE     Name                 1994-02-09 16:37:50.6  CNTL      DAEFCOC
__ SEATTLE     External             1994-02-09 16:37:51.0  CNTL      DAEFCOC

Cmd:                               Position to Node _____ CD Name DAEFCOC
  DI Display MO Modify ER Erase
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Menu  Quit  Add              ErAll  -    +    --    ++
Mark item(s) from the list above with a command or press a PF-key

```

You can display, modify or erase each profile displayed on this screen.

Node Name

The transport service node responsible for uploading the address to the central directory.

Addressee Type

Type of addressee that will be imported. It can be one of the below:

Name Con-nect user.

Address Nickname.

Cabinet Private, shared, standalone, or public cabinet.

Bulletin Bulletin board.

External External address.

Date Last Downloaded

Date and time last download was performed.

(Batch Import) Mode

Indicates how the addresses are imported to your SYSCNT cabinet in batch mode.

AUTO Addresses which pertain to this profile are imported automatically.

CNTL Addresses will only be imported on line so that you can control the import of each address.

CD Name

Name of central directory.

Position to Node

If you wish to begin the list starting with a particular node, enter the node name in this field and press ENTER. As a result, the list is restarted with the node you specified.

Additionally, you can press PF4 to add a new profile. As a result, you are returned to the "Directory Synchronization - Add Profiles" screen. See *Add Profiles*.

Display Profile

To display the profile of an addressee type, enter DI in the Cmd column for the appropriate node name and addressee type, and press ENTER.

Erase Profile

To erase the profile of an addressee type, enter ER in the Cmd column for that profile, and press ENTER. As a result, a confirmation window is displayed. You can either confirm (Y) or cancel (N) the deletion of each marked profile individually, or you can enter an asterisk (*) to confirm the deletion of *all* marked profiles.

To erase all profiles displayed on this screen, press PF6. As a result, a confirmation window is displayed. Enter Y and press ENTER to erase all profiles, or press ENTER to cancel.

Modify Profile

To modify the profile of an addressee type, enter MO in the Cmd column for the appropriate node name and addressee type, and press ENTER. As a result, the screen below is displayed.

| | | | |
|---|--|--------------------|-----------|
| 6:06 PM | * * * C O N - N E C T 3 * * * | | 14.Feb.94 |
| Cabinet LS | Directory Synchronization - Modify Profile | | OLIP92 |
| Download | | Import Rule Syntax | |
| CD Name: | DAEFCOC_ | #1 #2 ... | |
| Node Name: | DENVER__ | #1 Mail ID | |
| Addressee Type: | Bulletin_____ | #2 Node Name | |
| Date Last Downloaded: | 1994-02-09 16:37:50.4 | #3 Last Name | |
| Highest Transaction ID: | 00000000000000000000056600 | #4 First Name | |
| | (Set to zero with RESET PF-key) | #5 CD Name | |
| | | #6 Alias | |
| | | #7 Addressee | |
| Import | | | |
| Separator: | . | | |
| Import Rule: | #2 #7_____ | | |
| Exception Import Rule: | #6_____ | | |
| Batch Import Mode: | _ Automatic X Controlled | | |
| Target Cabinet: | SYSNT__ | | |
| Folder: | Work_____ | | |
| File: | DENVER ADDR_____ | | |
| Security Levels: | 7 Read 7 Modify 7 Copy 7 Print | | |
| | (Original security levels used when blank) | | |
| Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12--- | | | |
| Help Menu Quit | | Reset | Cancel |
| Make the required changes and press a PF-key | | | |

Notes:

1. Some fields are only shown for specific addressee types. For example, when the addressee type is "Bulletin", the "Include First/Last Name" field is not shown.
2. If user exit USR0060C (see *User Exit USR0060C*) is used to create the addressees' nicknames, then the fields "Include First/Last Name", "Separator", "Import Rule" and "Exception Import Rule" are not displayed.

With the exception of the target cabinet, you can modify all information pertaining to the Import Addresses function. You cannot modify the information pertaining to the download function with the exception of the Highest Transaction ID field.

To reset the highest transaction ID to zero you press PF6. This forces the system to perform a total download with the next download. This means that, if you have erased previously uploaded addresses from your node, these addresses will be again downloaded. See *Erase Imported Addresses from Your Con-nect Node*.

Once you have completed your modifications, press PF3 to save your changes.

If you have marked several addressee types for modification, you can press PF4 to display the next addressee type.

Maintain Log Records

Depending upon the log level you specified with the Directory Synchronization Maintenance function, either all significant events that occur, or only specific events are recorded in the log record. See *Directory Synchronization Maintenance*.

The log information is used to facilitate problem determination and general supervision. To avoid excessive disk space usage, you should occasionally delete obsolete log data.

| | | | | | | | |
|---|----------|---|------------|------------|---------------------------|-----------|------------------|
| 6:11 PM | | * * * C O N - N E C T 3 * * * | | | | 14.Feb.94 | |
| Cabinet LS | | Directory Synchr. - Maintain Log Information | | | | OLLP03 | |
| Cmd | Msg. Nr. | Program | Log Time | | Log Message | | Node Name |
| --- | ----- | ----- | ----- | | ----- | | ----- |
| ___ | 5087 | OLPN06 | 1994-01-25 | 13:00:54.2 | Program OLPN06 started at | | RESTON |
| ___ | 5087 | OLPN06 | 1994-01-25 | 13:00:54.5 | Program OLPN06 started at | | RESTON |
| ___ | 5087 | OLAN21 | 1994-01-25 | 13:02:51.0 | Program OLAN21 started at | | RESTON |
| ___ | 5087 | OLPN06 | 1994-01-25 | 13:02:51.2 | Program OLPN06 started at | | RESTON |
| ___ | 5030 | OLUP01 | 1994-01-26 | 10:24:39.6 | Upload utility has been c | | RESTON |
| ___ | 5110 | OLIN05 | 1994-01-26 | 10:26:33.7 | Address cannot be importe | | RESTON |
| ___ | 5087 | OLIP92 | 1994-01-26 | 10:26:46.6 | Program OLIP92 started at | | RESTON |
| ___ | 5110 | OLIN05 | 1994-01-26 | 10:29:13.4 | Address cannot be importe | | RESTON |
| ___ | 5110 | OLIN05 | 1994-01-26 | 10:29:13.7 | Address cannot be importe | | RESTON |
| ___ | 5110 | OLIN05 | 1994-01-26 | 10:29:13.8 | Address cannot be importe | | RESTON |
| ___ | 5110 | OLIN05 | 1994-01-26 | 10:29:13.9 | Address cannot be importe | | RESTON |
| ___ | 5110 | OLIN05 | 1994-01-26 | 10:29:46.3 | Address cannot be importe | | RESTON |
| ___ | 5124 | OLIN05 | 1994-01-26 | 10:29:56.4 | 0 addresses imported - 37 | | RESTON |
| ___ | 5087 | OLIP92 | 1994-01-26 | 10:34:55.5 | Program OLIP92 started at | | RESTON |
| Cmd: | | Position to Current Node Name ALSBACH_ Log Time | | | | | _____ |
| DI Display | | ER Erase TO Top | | | | | YYYYMMDDHHMMSSST |
| Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12--- | | | | | | | |
| Help Menu Quit | | ErAll - + -- ++ | | | | | |
| Mark item(s) from the list above with a command or press a PF-key | | | | | | | |

Msg. Nr.

Message number.

Program

Name of program which generated the log record.

Log Time

Date and time log record was created.

Log Message

Information used for tracing.

Node Name

Node on which event occurred.

Position to Current Node Name

By default, the log messages recorded on your node are displayed. If, for example, you have modified your node name, you can enter the name of your previous node name to display the log records that were created with this node.

Log Time

If you want to begin the list with logs created on a particular day and/or time, enter the date and time in this field and press ENTER. As a result, the list is restarted with log records which occurred since the time you specified.

You can mark any log record with ER in the Cmd column to erase the record from the file. As a result, a window is displayed where you are asked to confirm the erasure; enter Y and press ENTER. To cancel the erasure, press ENTER.

Additionally, you can mark each log record item with DI in the Cmd column to obtain extended information about the record. As a result, a screen similar to the one below is displayed.

```

5:02 PM          * * * C O N - N E C T 3 * * *          14.Feb.95
Cabinet LS      Directory Synchr. - Display Log Information  OLLP03

Program  OLUP01          Message Number  5030
Log Time 1994-11-21 10:14:50.4      Function  UPLOAD
                                   Node  ECUADOR
Log Message      Log Level Threshold  1      Logged with level

Upload utility has been completed
Records Synchronized 0 Node ECUADOR

1

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      Help  Menu  Quit                                   Canc1
Press a PF-key

```

The information displayed here is used to assist the Software AG staff if additional information is required.